

Solaris printing to MacOSX printer

How to configure a print queue in Solaris which delivers to a MacOSX print queue

```
root@zion /# lpadmin -p printername -s osxprintserverhostname -o banner=never
root@zion /# lpadmin -d printername
```

Verification

```
root@zion /# lpstat -p brother1_loopback_org -l
printer brother1_loopback_org idle. enabled since Mon Sep 21 09:58:46 2009. available.
Form mounted:
Content types: application/octet-stream, application/pc-eps, application/pdf, application/pictwps, application/postscript, application/vnd.apple-postscript,
application/vnd.cups-postscript, application/vnd.cups-raw, application/vnd.hp-hpgl, application/x-cshell, application/x-csource, application/x-perl,
application/x-shell, image/fuji-raw, image/gif, image/imageio, image/jp2, image/jpeg, image/minolta-raw, image/openexr, image/pict, image/png, image
/rad, image/tiff, image/x-alias, image/x-bitmap, image/x-bmp, image/x-ico, image/x-icon, image/x-photocd, image/x-portable-anymap, image/x-portable-
bitmap, image/x-portable-graymap, image/x-portable-pixmap, image/x-psd, image/x-qtif, image/x-sgi-rgb, image/x-sun-raster, image/x-tga, image/x-
xbitmap, image/x-xpixmap, text/html, text/plain, text/rtf,
Description: Brother MFC-8860DN
Printer types:
Connection:
Interface:
After fault: continue
Users allowed:
(all)
Forms allowed:
(none)
Media supported:
Upper
Letter
Legal
A4
ISOB5
JISB5
LetterSmall
LegalSmall
A4Small
Banner page never printed
Character sets:
(none)
Default pitch:
Default page size:
Default port setting:
Options:
```

```
root@zion /# lpstat -a
```

```
brother1_loopback_org accepting requests since Mon Sep 21 10:01:02 2009
```

```
root@zion /# lpq
```

```
no entries
```

(see <http://docs.sun.com/app/docs/doc/819-7761/gfjix?a=view>)